

BS2000/OSD Considerations

This section describes BS/2000 considerations.

It covers the following topics:

- How to Start/End Entire System Server on BS2000/OSD
 - Details for Running Entire System Server on BS2000/OSD
 - Aspects of Running System Automation Tools in Entire System Server on BS2000/OSD
 - BS2000/OSD Security Considerations
 - BS2000/OSD SECOS Considerations
 - BS2000/OSD UCON Interface
 - BS2000/OSD System Command Interface
-

How to Start/End Entire System Server on BS2000/OSD

Single-User Mode

All modules required to perform an Entire System Server function are dynamically loaded into the caller's address space at request. You must therefore assign the Entire System Server Module Library to link name DDLIB2 before the Natural session is started.

A startup parameter file should be assigned to link name PARMS. If not, the default values for all startup parameters are used as far as they exist. For example, the parameter PRODUCT has no default and therefore no LMS functions can be performed if no startup parameter file is assigned.

The Entire System Server session is terminated when the Natural session is terminated.

Multi-User Mode

To use Entire System Server in multi-user mode, an Entire System Server node must have been started, that is, the Entire System Server MAIN task must have been started. All other tasks required for an Entire System Server node will then be automatically started by the MAIN task. See also Step 8: Edit the Entire System Server Start Jobs of the Installation for BS2000/OSD.

Shutdown of Entire System Server on BS2000/OSD

There are several ways to terminate an Entire System Server node. The usual method is to issue the console command

```
/INTR <tsn>,ADAEND
```

where <tsn> is the TSN assigned to the MAIN task.

This will automatically end all tasks belonging to that Entire System Server node.

The UCON interface task is not terminated by this because it may still be used by another node. It can however be terminated via the console command

```
/BCLOSE <application-name>
```

where *<application-name>* is the name which was assigned in the JCL of the UCON interface task. See also Step 8: Edit the Entire System Server Start Jobs of the Installation for BS2000/OSD.

For information on how to terminate Entire System Server via operator command, see Section Operator Commands in the Entire System Server Administration Documentation.

Another way to terminate an Entire System Server node is to issue FUNCTION= 'XEND' in the view processor NATPROC-USERS.

From Version 3.1.1 of Entire System Server, you can run the program ESYSTOP to shutdown ESY. It must be executed with the same user ID as the Entire System Server, i.e., as user TSOS.

The program ESYSTOP is driven by parameters obtained from SYSDTA. Job name or TSN of the ESY-MAIN task can be specified. The following syntax must be used for the parameters:

```
-J jobname | --JNAME jobname
-T tsn     | --TSN tsn
```

The parameter --JNAME is recommended for a generic setup of program ESYTRACE.

A sample job is listed in Step 8: Edit the Entire System Server Jobs of the Installation for BS2000/OSD.

Details for Running Entire System Server on BS2000/OSD

- Tasks
- Communication
- Library Concept
- Program Characteristics

Tasks

Entire System Server under BS2000/OSD consists of several tasks.

The MAIN task is started manually by the operator or by a startup script. This main task spawns a number of other tasks according to the definitions in the startup parameter file.

Problems arise, if the JOB-CLASS-LIMIT of the operating system is exhausted.

Entire System Server cannot work properly, if some ESY tasks are still hold in the wait queue. This state must be avoided by appropriate operator interventions.

A TIMER-controlled routine in the MAIN task regularly checks the state of all ESY tasks, e.g., the status of the started server tasks and their workload.

Communication

Communication between the different ESY tasks is established via Eventing and Common Memory Pools. Forward Eventing is used for performance reasons.

The Natural applications and Entire System Server use the Adabas communication for transport of user data and for mutual communication between the different address spaces. The ESY node is addressable like an Adabas nucleus and thus visible via appropriate utilities.

Library Concept

The library concept of Entire System Server under BS2000/OSD has been completely revised for Version 3.1.1.

The modules are link-edited to reduce the ESY startup duration. Apart from that, there is a strict distinction between the delivery library and the user library. While the delivery library contains the original ESY modules only, Customers user exits are kept in the ESY user library.

All ESY startup jobs contain the assignment of the ESY module library via LINK-NAME 'DDLIB2' and the assignment of a customer-specific ESY user library via LINK-NAME 'BLSLIB00'. This user library is searched for required modules alternatively, if nothing was found in the library assigned via LINK-NAME 'DDLIB2'.

To run different configurations, some modules must be loaded dynamically.

Program Characteristics

From Version 3.1.1, all Entire System Server components run in AMODE 31 (AMODE = addressing mode). This is independent from settings in the job control.

At program termination, the Entire System Server components set a return code, which is transferred to a monitoring job variable.

The status display for successful execution is C' \$T 0000', the status for abnormal termination is C' \$A 0008'.

Aspects of Running System Automation Tools in Entire System Server on BS2000/OSD

General

Entire System Server enables the operation of System Automation Tools (e.g., Entire Output Management (EOM), Entire Operations (EOR)) as subtasks in the address space of ESY (OS/390, VSE/ESA) or as pseudo subtasks, i.e., standalone tasks (BS2000/OSD). These System Automation Tools (SAT) are applications on the basis of Natural, which require a Batch-Natural as engine.

SAT products are started by means of ESY startup parameters.

This section offers an overview of the interfaces between ESY and SAT and deals with the configuration in the overall context.

Activating SAT during Start of Entire System Server

Start of SAT under BS2000/OSD

As Natural subtasks are implemented as separate tasks under BS2000/OSD, the definition of job control instructions is required. The ESY startup parameter JOBNATSUB specifies the location of the SAT-ENTER job. Apart from that, the following can be defined:

- the attributes for the SAT-ENTER job (PRMNATSUB parameter)
- the maximum number of pseudo Natural subtasks (NATNUMSUB parameter)
- and from ESY Version 2.2.2, the input control of dynamic Natural parameters (NATDYNPAR parameter).

The SAT-ENTER job, which is started during the initialization of Entire System Server, reads initialization data and starts the configured SAT products according to the set up definitions.

In general, a distinction must be made between the start of the SAT products via the macros SATSTART TYPE=BATCH and SATSTART TYPE=SUBTASK. To obtain a complete interaction of the SAT products with ESY, the SATP member (see SAT Installation and Customization for details) for the SATSTART macros should always use the TYPE=SUBTASK type. This ensures that both control functions and the Entire System Server shutdown interact with the SAT subproducts. TYPE=BATCH jobs are not known to Entire System Server.

The products started by SAT (e.g., EOM, EOR) run via separate ENTER jobs. In case of SATSTART TYPE=SUBTASK a job-skeleton is used for these ENTER tasks, which in the past had to be part of the ESY module library in object module format. From ESY 3.1.1, this job skeleton is definable as part of the ESY startup file.

Recently Introduced Startup Parameters under BS2000/OSD

- ESY 2.2.2: NATDYNPAR startup parameter for the operation of SAT products

The ESY startup parameter NATDYNPAR was introduced to support reading the dynamic Natural parameters from FILE, SYSDTA or SYSIPT according to the definition in the Batch-NATURAL driver. The NATURAL-SUB-TASK skeleton has been changed therefore to handle these different NATDYNPAR settings.

- ESY 3.1.1: NATURAL-SUB-TASK job skeleton as part of the ESY startup parameter file

The job skeleton must not be converted into object module format any more. It can be defined at any location in the ESY startup parameter file and must be started using the keyword SATSKEL-BEGIN and terminated with the keyword SATSKEL-END.

The jobs P.NSBTSKIS and P.NSBTSKSD are still delivered as ESY source library elements, but they are only included for compatibility reasons.

The following abridged example of an ESY startup parameter file illustrates the keyword usage:

```
NODE=113
TIME=30
... more parameters ...
JOBNATSUB=$NPR.E.SAT.113
PRMNATSUB=RESOURCES=*PAR(CPU-LIMIT=*NO)
NATDYNPAR=FILE
NATNUMSUB=20
*
SATSKEL-BEGIN
/.&UID LOGON
... more JCL ...
/ LOGOFF SYS-OUT=DEL
SATSKEL-END
```

A complete example is part of the delivery files. A comprehensive description is provided in the Section Startup Parameters.

Control of SAT during Entire System Server Operation

Starting with ESY 3.1.1, the enhanced LIST function of view NATPROC-USERS displays all internal tasks in addition to the ESY users, if the new field FULL-SCAN = 'YES' has been specified. It allows to control ESY tasks with a Natural program.

Activating/Deactivating NATURAL-SUBTASKS (SAT) during ESY Operation

The operator command "SHUTDOWN" stops SAT components. New with ESY 3.1.1 is the operator command "START ALL" to restart SAT without restarting ESY. The SAT mother task will be started again to respawn all configured ESM monitors. "START ALL" may be used only if the entire SAT environment has previously stopped on its own or has been stopped by operator command "SHUTDOWN ALL". Both commands in conjunction allow to "bounce" SAT during normal operation of ESY.

Please note that the operator command SHUTDOWN can address individual SAT products via parameters while the START command only accepts parameter ALL.

Deactivating SAT during Entire System Server Stop

Entire System Server must stop all NATURAL-SUB-TASKS before shutting down. The stop request is published by ESY to all ESM monitors. Having communicated the termination information, ESY checks the status of the NATURAL-SUBTASKS over short time intervals. If they have terminated on their own, shutdown will be continued. In the meantime, user requests are still processed, as if the shutdown command had not been issued.

This procedure is called "Deferred Shutdown".

New startup parameter SHUTDOWN-MAX-DELAY limits the Deferred Shutdown to a specified number of seconds. If the time limit is reached, Entire System Server will terminate without properly closing down the SAT tasks.

If this situation occurs, you must check why the SAT products did not stop within the defined time interval. In this case, Software AG support should be consulted, if necessary.

As the SAT monitors have wait cycles, SHUTDOWN-MAX-DELAY=180 should be used initially. If all NATURAL-SUB-TASKS are stopped, the ESY termination will be continued without further delays.

BS2000/OSD Security Considerations

The Entire System Server tasks access datasets and other resources as requested by the Natural user. To be able to do this for various users, the Entire System Server must run under BS2000/OSD user ID TSOS. Users' access rights are checked by the Entire System Server in order to provide access to BS2000/OSD objects in the same range as if working under TIAM. Therefore, the Natural user must identify himself to Entire System Server before any view can be accessed.

A logon operation must be performed, specifying the user's system user ID and password. If SECURITY=BS2 was specified in startup parameters, user ID and password are checked against the system's user definition file (TSOSJOIN). If this validation is successful, the user ID will from then on be used for future validations until it is changed by another logon operation.

If the user attempts to access a view before logging on, Response Code **510** (LOGON REQUIRED) is returned. However, if the startup parameter AUTOLOG is set to YES, an implicit logon is performed as part of the first user request.

If the Natural user ID (BS2000/OSD logon user ID for batch, or TIAM, *USER for UTM) is not defined in BS2000/OSD, Response Code 510 (LOGON REQUIRED) is returned. For Natural/UTM, TSOS is not allowed as *USER and will be rejected.

The Entire System Server online tutorial contains a sample logon program that uses view NATPROC-LOGON.

The logon operation is not needed if Entire System Server is used in single-user mode.

If SECURITY=USER is specified in the startup parameters, exit USERLSEC is called to check the user ID and password as required at your site, and not against the system's user definition file (TSOSJOIN). For a sample exit USERLSEC, see the supplied Source Library.

If no security system interface is requested (startup parameter SECURITY=NONE), no security check is performed: all logon attempts will be successful. If in this case the Natural user ID is not defined in BS2000/OSD, only functions which do not require a BS2000/OSD user ID are available (such as EVENTING).

BS2000/OSD SECOS Considerations

If the Siemens software product SECOS is installed at your site, please note that the Entire System Server must be authorized to access any object that any of its users should be able to access.

This means that the Entire System Server user ID (TSOS) has to be defined in every access control list (ACL) of those objects. For SECOS V2 it is sufficient to define the program SERVER from the Entire System Server Module Library in any GUARD concerned, if GUARDs are used.

BS2000/OSD UCON Interface

The Entire System Server can run without the UCON interface. However, it is required if you wish to use views SEND-MESSAGE or CONSOLE.

The UCON interface of Entire System Server is activated by a separate task which opens a DCAM application and connects to UCON (\$CONSOLE).

To enable the UCON interface task to connect to UCON, an authorization name must be defined for Entire System Server in BS2000/OSD generation and this name must be defined as BS2000/OSD user ID. This user ID, as well as the password defined for it must be specified as parameter of program ESYCONS in the JCL to start the Console Task of Entire System Server. (See also Step 8: Edit the Entire System Server Start Jobs of the installation of BS2000/OSD.)

The user ID must be authorized to issue certain operator commands. ESY does not require operator command authorization keys but the ESM monitors do. Therefore, the user ID must be authorized to issue all operator commands needed by the ESM monitors to support full functionality. For example, Entire Output Management needs the authorization key of operator command /CANCEL-JOB.

The required authorization keys for the UCON user ID are listed in the manuals of the various ESM products.

If your application issues operator commands, the UCON user ID must be authorized by the Administrator to execute that command.

The UCON interface task (also referred to as **console task**) can be shared by all Entire System Server nodes running on the same BS2000/OSD. With startup parameter CONACCESS, use of console functions can be restricted for all users on that node.

If WRITE is specified for CONACCESS, an exit can be used to further restrict use of the OP-CMD function of the CONSOLE view. Whenever the CONSOLE view is called with FUNCTION=OP-CMD, the USERCSEC module in the Entire System Server User Module Library gets control (if it exists). The caller's user ID, as well as the command string, are passed to the exit as input parameters and the exit checks whether the user is authorized to issue the command. If user exit USERCSEC does not exist, all operator commands will be accepted.

For a sample exit USERCSEC, see the supplied Source library. For a description of the CONACCESS parameter, see the section Startup Parameters.

BS2000/OSD System Command Interface

The SYSTEM-COMMAND view allows to issue a BS2000/OSD command in a Natural program. The view passes the data to the macro command language processor and returns the result to the calling Natural application.

An exit must be activated to restrict the use of system commands. Whenever the **SYSTEM-COMMAND** view is called, the **USERSSEC** module in the Entire System Server User Module Library gets control (if it exists). The caller's user ID, as well as the command string, are passed to the exit as input parameters and the exit checks whether the user is authorized to issue the command. If user exit **USERSSEC** does not exist, view **SYSTEM-COMMAND** is completely disabled.